

# **Radiography and Ultrasonic Calculation Workbooks: Installation and Use**

*D. Rikard, K. Dolan*

**March 24, 2000**


***U.S. Department of Energy***

Lawrence  
Livermore  
National  
Laboratory

## **DISCLAIMER**

This document was prepared as an account of work sponsored by an agency of the United States Government. Neither the United States Government nor the University of California nor any of their employees, makes any warranty, express or implied, or assumes any legal liability or responsibility for the accuracy, completeness, or usefulness of any information, apparatus, product, or process disclosed, or represents that its use would not infringe privately owned rights. Reference herein to any specific commercial product, process, or service by trade name, trademark, manufacturer, or otherwise, does not necessarily constitute or imply its endorsement, recommendation, or favoring by the United States Government or the University of California. The views and opinions of authors expressed herein do not necessarily state or reflect those of the United States Government or the University of California, and shall not be used for advertising or product endorsement purposes.

This work was performed under the auspices of the U. S. Department of Energy by the University of California, Lawrence Livermore National Laboratory under Contract No. W-7405-Eng-48.



# **Radiography and Ultrasonic Calculation Workbooks: Installation and Use**

**Derrill Rikard / Ken Dolan**

Nondestructive Evaluation Section, Lawrence Livermore National Laboratory

## **Background** \_\_\_\_\_

The radiography and ultrasonic calculation workbooks are intended to assist Level I, II and III NDE personnel in calculations used in routine job applications. These workbooks are an upgraded version of Microsoft Excel® spreadsheets, which were originally set up in October 1988, using a Macintosh Plus® computer and Microsoft Excel® version 1.5. A description of these was released as "Computerized Calculations for Radiography and Ultrasonics", UCRL-JC-105419 in November 1990 and published in Materials Evaluation, Volume 49/ Number 4, in April 1991. Over the years as Microsoft improved the capabilities of the Excel program to include the abilities to make sketches and to have multiple tabbed pages in a document called a "workbook", we have now modified the calculation spreadsheets to include these enhancements.

Following is a short description on how to install and use these workbooks on a Macintosh or PC.

## **RT Workbook Installation** \_\_\_\_\_

Drag the "RT Workbook" icon onto your desktop or into the folder where you want the icon to reside. Double click the icon to open it. On the Macintosh, If the workbook is locked, it will display the message illustrated in Figure 2. Click on "OK" to open the workbook. The workbook will operate the same whether it is locked or unlocked, but it is recommended that the workbook after installation be locked to prevent accidental changes to the formulas in the calculation cells.




Figure 1

Figure 1 shows how the Index page should look on your computer screen. If the page tabs along the bottom edge of the workbook or the scroll bar on the right side of the window is not visible on your computer screen; you must arrange the window. The workbook must be unlocked to do this. To unlock the workbook, close the workbook then click the mouse once on the icon to select it. The icon will then turn black. On the Macintosh go to File on the Menu bar, go to Get Information, then click the mouse on the Locked box on the lower left side of this window. The checkmark in this box will disappear and the file will be unlocked. On a PC to unlock the workbook, go to Tools in the Menu bar, go to Protect Workbook then click the mouse on Protect Structure and Protect Windows to delete the checkmarks. The file will now be unlocked.

Double click the mouse on the icon to open the workbook. The locked warning in Figure 2 should NOT BE DISPLAYED when the window opens.



**Figure 2**

Arrange the window on a Macintosh or a PC by pressing the mouse on Window in the Menu bar, drag the cursor down to Arrange All, click the mouse on Tiled then click on "OK". The workbook should now look like Figure 1. The Scroll bar on the right side of the page is used to scroll up and down the pages and the tabs along the bottom edge of the workbook are used to go to the individual calculation pages.

The workbook should now be locked.

On the Macintosh to lock the workbook you should have it saved with the Index page displayed as it is in Figure 1. Go to File on the Menu bar, go to Get Information and click the mouse on the Locked box on the lower left side of this window. A checkmark will appear in the box. With the workbook saved and locked in this manner it will always open on the Index page. If a formula is accidentally changed, it will not be a permanent change; the next time the workbook is opened, it will revert back to the original formula.

Each time the workbook is opened after being locked, the message in Figure 2 is displayed. Click the mouse on "OK" to continue.

To Lock the workbook on a PC you should have it saved with the Index page displayed as it is in Figure 1. Go to Tools in the Menu bar; drag down to Protection, then to Protect Workbook. Click the mouse on Protect Structure and Protect Windows. Checkmarks will appear in these boxes.

## **UT Workbook Installation**

---

Drag the "UT Workbook" icon onto your desktop or into the folder where you want the icon to reside Double click the icon to open it. On the Macintosh, if the workbook is locked, it will display the message illustrated in Figure 2. Click on "OK" to open the workbook. The same procedure as previously described should be used to arrange and lock the "UT Workbook". This workbook does not have an Index and has only a single page of formulas so only the scrollbar on the right side is used to find the appropriate calculation.

## **RT Workbook Operation**

---

From the Index page in the "RT Workbook" an individual page is used for the different calculations necessary. For example, if you want to calculate where to place a 4" diameter collimator to obtain a 5" diameter field of view when using a source-to-film distance of 12 feet (144"), the following steps would be taken: 1) On the Index page in Figure 1 you see Collimator Location is on the Collimator page, so click the mouse on the Collimator Tab on the bottom edge of the workbook. 2) The mouse click will immediately go to that page. 3) Enter the parameters in the boxes provided for Source to Film Distance (144), Size of the Collimator Image on the Film (5) and the Collimator Hole Diameter (4). Press the Enter key or click the mouse in another cell outside of these boxes and the answer will be calculated and displayed in the left column. A source-to-collimator distance of 115.20 inches would be needed to obtain this field of view (see Figure 3). After you have finished with your calculations and want to quit the workbook, do not save the changes in the workbook by clicking the mouse on the Don't Save button.




Figure 3

## UT Workbook Operation

The same procedure as previously described should be used for calculations in the "UT Workbook". However, this workbook does not have an Index page and has only a single page of formulas so the scrollbar on the right side of the page is used to move up and down the page to find the appropriate calculation.

## Summary

These worksheets have been in use for many years now with many modifications as Microsoft Excel has improved. This short description and example is to help new users install the latest versions and get started using them. Other useful calculations can be added to these workbooks but remember to Unlock the workbook before making changes.

Direct questions, comments and suggestions to Derrill Rikard, LLNL, P.O. Box 808 L-333, Livermore, CA. 94551-0808, Phone (925) 442-7947 or E-mail rikard1@llnl.gov

## **INDEX**

---

### **Exposure Change**

Film DENSITY vs. TIME or MAS  
TIME or MAS vs DISTANCE  
TIME or MAS vs KILOVOLTAGE CHANGE  
INVERSE SQUARE LAW

### **Part Alignment**

Waist Alignment by Tilting the Part  
Alignment by Moving Source or Part  
Alignment When Center Area is Blocked by Tilting the Part  
Alignment When Center Area is Blocked by Moving the Source or Part  
Waist Weld Alignment Using Micrometer Fixture

### **Pipe or Tube**

Material Thickness on a Pipe or Tube

### **HVL & TVL**

HALF-VALUE LAYER / NARROW BEAM  
TENTH-VALUE LAYER / NARROW BEAM  
RADIOGRAPHIC EQUIVALENCE FACTORS

### **UG & Enlarge**

GEOMETRIC UNSHARPNESS  
OBJECT ENLARGEMENT

### **Collimator**

COLLIMATOR LOCATION  
ADJUSTMENT for COLLIMATOR LOCATION

### **PARALLAX VIEWS or DEFECT LOCATION**

RIGID FORMULA  
Double Marker Estimated Method - 2 markers are used and SFD and Tube Shift are Not Known.  
Defect Location from Front Surface using SOD and Front Marker Shift.

### **IQI INFO - Penetrameters**

MINIMUM & MAXIMUM FILM DENSITY for 1 PENETRAMETER  
Equivalent Penetrameter Sensitivity (Hole Type Penetrameter)  
Equivalent Wire Diameter to Produce the Same EPS as the Hole Type Penetrameter from above.



## **Trigonometry**

**TRIGONOMETRIC RATIOS on RIGHT TRIANGLES**

**LAW of COSINES**

**TRIGONOMETRY / LAW of SINES**

**CHORD LENGTH ON A CIRCLE**

## **Source RT**

**Cobalt Source Strength**

**Radiation Output from COBALT**

**Approximate COBALT-60 Exposure Time in Minutes**

**Iridium Source Strength**

**Radiation Output from Iridium**

**Approximate IRIDIUM-192 Exposure Time in Minutes**

## **MISC.**

**RADIATION INTENSITY**

**LINEAR ATTENUATION COEFFICIENT**

**AREAL DENSITY**

**RADIATION REDUCTION FACTOR**

**Linear Attenuation Coefficient for Mixture**

**IN-MOTION RADIOGRAPHY**

**Film DENSITY vs. VELOCITY**

**Volume of a Sphere**

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 2/17/00 by Derrill Rikard

Film DENSITY vs. TIME or MAS			
NEW time or MAS	Film DENSITY Wanted	First Film DENSITY	Old Time or MAS
1.14	2	1.8	1

TIME or MAS vs DISTANCE			
NEW TIME/MAS	OLD TIME or MAS	OLD DISTANCE	NEW DISTANCE
67.50	30	36	54

TIME or MAS vs KILOVOLTAGE CHANGE			
	OLD KILOVOLTAGE	OLD TIME or MAS	
	50	1	
Higher Kilovoltage	TIME or MAS @ Higher kV	Lower Kilovoltage	TIME or MAS @ Lower kV
60	0.5	42.5	2

INVERSE SQUARE LAW			
INTENSITY 2	Intensity 1	Distance 1	Distance 2
0.28	150	1	23
DISTANCE 2	Intensity 1	Intensity 2	Distance 1
327.33	18000	0.168	1
INTENSITY 1	Intensity 2	Distance 1	Distance 2
861.11	80	12	39.37
DISTANCE 1	Intensity 1	Intensity 2	Distance 2
43.00	2.38	2.38	43

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 3/2/99 by Derrill Rikard

#### Waist Alignment by Tilting the Part

Degrees to Tilt the Part

0.895


Measured Part Diameter	Measured Gap (Misalignment)
8.000	0.125

If the tilt needed to align the part is done by measuring the distance from the present position to the aligned position, use the following calculation to determine where to mark the new position on the front side of the part.

Distance to the New Location

0.059

Measured Part Diameter	Measured Gap (Misalignment)	Actual Part Diameter
8.000	0.125	7.500



Distance to Move  
the Source or Part

0.143

#### Alignment by Moving Source or Part

Source to Object Distance	Measured Part Diameter	Measured Gap (Misalignment)
45.600	8.000	0.025

#### Alignment When Center Area is Blocked by Tilting the Part

Degrees to Tilt the Part

0.902


Measured Part Diameter	Distance from Part Edge to Measurement Location	Measured Gap (Misalignment)
8.000	3.500	0.125

If the tilt needed to align the part is done by measuring the distance from the present position to the aligned position, use the following calculation to determine where to mark the new position on the front side of the part.

Distance to the New Location

0.065

Measured Part Diameter	Distance from Part Edge to Measurement Location	Measured Gap (Misalignment)	Actual Part Diameter
8.000	3.000	0.125	7.500



#### Alignment When Center Area is Blocked by Moving the Source or Part

Distance to Move Part

0.143

Measured Part Diameter	Distance from Part Edge to Measurement Location	Measure Gap (Misalignment)	Source to Object in IN.
8.000	4.000	0.025	45.600

Micrometer  
Correction



0.027

#### Waist Weld Alignment Using Micrometer Fixture

Max. Gap Measurement	Part Diameter-INCHES	Micr.to Leveling AXIS
0.050	4.688	2.5

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 11/18/99 by Derrill Rikard



#### Material Thickness on a Pipe or Tube

Matl Thickness at Location A - Double Wall Thickness  
0.052

Maximum Matl Thickness at Location B  
0.101

Matl Thickness at the Center of the Wall - Location C  
0.076

Outside Diameter of  
the Tube or Pipe  
0.125

Single Wall Thickness of Pipe or Tube  
0.026

#### NOTE:

To determine Material Thickness at other locations,  
Go to the bottom of the Trigonometry Page.

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 3/24/99 by Derrill Rikard

**HALF-VALUE LAYER / NARROW BEAM**  
 HVL in CM Linear Atten.in 1/CM  
 0.35   
 HVL in INCHES  
 0.14

**TENTH-VALUE LAYER / NARROW BEAM**  
 TVL in CM Linear Atten. in 1/CM  
 10.10   
 TVL in INCHES  
 3.98

**TYPICAL HALF-VALUE and TENTH-VALUE LAYERS in INCHES for COMMON ENERGIES**

Energy	ALUMINUM 1/2	ALUMINUM 1/10	STEEL 1/2	STEEL 1/10	LEAD 1/2	LEAD 1/10
120 kV	0.800	2.640	0.100	0.330	0.011	0.036
150 kV	0.880	2.900	0.140	0.462	0.011	0.036
200 kV	1.000	3.300	0.200	0.660	0.019	0.063
250 kV	1.100	3.630	0.250	0.825	0.035	0.116
400 / Ir192	1.300	4.290	0.350	1.150	0.087	0.287
2 MeV / Co60	2.500	8.250	0.800	2.640	0.500	1.650
4 MeV	3.600	11.880	1.000	3.300	0.650	2.140
9 MeV	4.570	15.000	1.250	4.125	0.650	2.140

**RADIOGRAPHIC EQUIVALENCE FACTORS**

Equal to this Thickness of Fe or ?? Matl. by Method Listed Below	Density of Fe or ?? in grams / cm <sup>3</sup>	Linear Attenuation of Fe or ?? in 1/cm	Density of Material in grams / cm <sup>3</sup>	Linear Attenuation of Material in grams / cm
	7.87	0.334	16.6	0.73
Thickness of Material	<input type="text" value="1"/>			

- 2.109 Density Only
- 2.186 Linear Attenuation Only
- 4.610 Both Density & Linear Attenuation

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 8/21/00 by Derrill Rikard

UG-in INCHES  
0.00168  
INCHES Min. SFD  
17.748  
SPOT Size in MM  
0.183

#### GEOMETRIC UNSHARPNESS

Focal Spot Size in MM	Part Thickness + Offset	Source-Film-Distance
2	6	288
MAX. UG Allowed	Focal Spot in MM	Part Thick + Offset
0.02	4	2
UG- in INCHES	SOD in INCHES	OFD in INCHES
0.007874	8.25	9

Object Size  
12.05  
Image Size  
22.59  
SFD  
840.00  
SOD  
1.88

#### OBJECT ENLARGEMENT

Image Size	SOD	SFD
22.6	1.6	3
SFD	Object Size	SOD
96	16	68
Image Size	SOD	Object Size
30	28	1
SFD	Image Size	Object Size
37.625	20	1

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 2/25/99 by Derrill Rikard

SOURCE to COLLIMATOR DISTANCE	COLLIMATOR LOCATION		
	Source to Film Distance	SIZE of Collimator Image on Film	Collimator Hole Diameter
115.20	144	5	4
Collimator Hole Diameter	SIZE of Collimator Image on Film	SOURCE to Collimator DISTANCE	Source to Film Distance
	12	96	288
SIZE of Collimator Image on Film	Source to Film Distance	Collimator Hole Diameter	SOURCE to Collimator DISTANCE
	288	4	96

NEW FILM to COLLIMATOR DISTANCE	ADJUSTMENT for COLLIMATOR LOCATION		
	OLD FILM to COLLIMATOR DISTANCE	OLD IMAGE SIZE	IMAGE SIZE WANTED
90.00	72	4	5

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 2/25/99 by Derrill Rikard

### PARALLAX VIEWS or DEFECT LOCATION

Double Exposure made on ONE film which has been Shifted between Exposures.

#### RIGID FORMULA

Flaw Above Film

0.274

Flaw position change	Source to Film Dist.	Tube Shift
0.055	60	12

### Double Marker Estimated Method - 2 markers are used and SFD and Tube Shift are Not Known.

Flaw Above Back Marker

0.240

Flaw Position Shift	Part Thickness	Front Marker Shift	Back Marker Shift
0.055	0.625	0.135	0.005

### Defect Location from Front Surface using SOD and Front Marker Shift.

FRONT FACE to Flaw

0.395

Flaw Position Shift	Source to OBJECT	Front Marker Shift	Tube Shift
0.055	59.5	0.135	12



TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 3/2/99 by Derrill Rikard

MIN. Film Density  
1.96  
MAXIMUM Film Density  
2.99

**MINIMUM & MAXIMUM FILM DENSITY for 1 PENETRAMEETER**  
**( All Film Densities must meet the CODE or SPECIFICATION)**  
FILM DENSITY through the PENETRAMEETER BODY & SHIM  
2.3  
THROUGH THE WELD'S AREA OF INTEREST

EPS in percent  
2.00  
IQI Thickness In.  
0.005  
Hole Diam. In.  
0.040

**Equivalent Penetrameter Sensitivity (Hole Type Penetrameter)**

IQI Thickness in Inches	Hole Diam. in Inches	Material Thickness in inches
0.005	0.04	0.5
Hole Diam. in Inches	EPS in percent	Material Thickness in inches
0.04	2	0.5
IQI Thickness in Inches	EPS in percent	Material Thickness in inches
0.005	2	0.5

from: ASTM E-1025

Equivalent  
Wire Diameter  
0.006

**Equivalent Wire Diameter to Produce the Same EPS as the Hole Type Penetrameter from above**

Plaque Thickness in Inches	Hole Diam. in Inches
0.01	0.02


from: ASTM E-747

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.


Updated 11/18/99 by Derrill Rikard

# TRIGONOMETRIC RATIOS on RIGHT TRIANGLES


SINE of ANGLE		
Angle A Degrees	Side Opposite A	Hypotenuse
0.333	0.25	43
TANGENT of ANGLE		
Angle A Degrees	Side Opposite A	Side Adjacent A
0.199	0.25	72
COSINE of ANGLE		
Angle A Degrees	Side Adjacent A	Hypotenuse
18.407	40.8	43




LAW of COSINES			
Side C Length	Side A Length	Angle Between Sides	Side B Length
7.000	8	60	5



TRIGONOMETRY / LAW of SINES			
Angle a	Angle b	Side A	Side B
20.71	50	1500	3250
Angle b	Angle a	Side B	Side A
49.98	20.7	3250	1500
Side A	Angle a	Side B	Angle b
1499.64	20.7	3250	50
Side B	Angle a	Side A	Angle b
3250.77	20.7	1500	50



CHORD LENGTH ON A CIRCLE		
CHORD LENGTH	Distance From Outside Edge To The CHORD	DIAMETER of Circle
0.887	0.005	39.37



## NOTE:

To determine thickness of a wall thickness on a tube or pipe,  
Subtract the ID chord length from the OD chord length.

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 2/25/99 by Derrill Rikard

**COBALT**  
671.44

### COBALT Source Strength

Original Activity	ON CAL.DATE	Present Date
1100	5/23/73	3/1/77

mR/Hr.

1316.86

DISTANCE in FEET

540.13

Source Strength-Ci

4.00

### Radiation Output from COBALT

Source Strength-Ci.	Distance in FEET
117.7	36
Source Strength-Ci.	mR/Hr.
50.3	2.5
mR/Hr.	Distance in FEET
580	10

### Approximate COBALT-60 Exposure Time in Minutes for a 2.0HD on 10pb/Dupont 55/10pb Film Load.

Time in Min.

2.31

Curies	Distance in Inches	Steel Thickness in Inches
100	24	2

**IRIDIUM**  
41.96

### IRIDIUM Source Strength

Original Activity	ON CAL.DATE	Present Date
100	9/9/88	12/12/88

mR/Hr.

520000.00

DISTANCE in FEET

29.94

Source Strength-Ci

100.00

### Radiation Output from Iridium

Source Strength-Ci.	Distance in FEET
100	1
Source Strength-Ci.	mR/Hr.
100	580
mR/Hr.	Distance in FEET
208	50

### Approximate IRIDIUM-192 Exposure Time in Minutes for a 2.0HD on 5pb/Dupont 55/10pb Film Load.

Time in Min.

14.52

Curies	Distance in Inches	Steel Thickness in Inches
200	48	2

TO FIND VALUE IN LEFT COLUMN, TYPE IN THE VALUES WITHIN THE BOXES ON THE RIGHT.

Updated 2/25/99 by Derrill Rikard

#### RADIATION INTENSITY

Second Intensity	Original Intensity	Linear Atten.in1/CM	Thickness in CM
0.168	18000	0.228	50.8

#### LINEAR ATTENUATION COEFFICIENT

Linear Atten. in 1/CM	Mass Absorption Coef.	Physical Density CC
3.287	0.279	11.78

#### AREAL DENSITY

AREAL DENSITY mg/cm2	Thickness in CM	Physical Density Mg/CC
59.69	1.27	47
Thickness in CM	AREAL DENSITY mg/cm-2	Physical Density Mg/CC
1.27	59.69	47
Physical Density Mg/CC	AREAL DENSITY mg/cm-2	Thickness in CM
47.00	59.69	1.27

#### RADIATION REDUCTION FACTOR

Reduction Factor	Dose Rate Wanted	Initial Dose Rate
90.00	0.5	45

#### PIN HOLE METHOD For FOCAL SPOT SIZE

Focal Spot in IN.	Pin Hole Set at 1/2 the SFD	Diam.of Hole Image	Actual Hole Diam.
0.045		0.125	0.04
Focal Spot in MM			
1.143			

#### Linear Attenuation Coefficient for Mixture

Lin.Atten Coeff 1/cm	Mass Atten Coef.1	Mass Atten Coef.2	Mass Atten 3	Mass Atten 4
0.006	3.8	5.91	65.4	0
	Per Cent 1	Per Cent 2	Per Cent 3	Per Cent 4
	75.6	23.1	1.3	0

#### DENSITY OF MATERIAL in GM/CC

0.001209
----------

#### IN-MOTION RADIOGRAPHY

Motion Unsharpness	Material Thickness	Width of Beam	Source to Part Distance
0.004	0.5	0.3	42
Beam Width	Motion Unsharpness	Material Thickness	Source to Part Distance
0.42	0.005	0.5	42
Velocity	Width of Beam	Time for Single Exposure	
0.30	0.3	1	
Exp.TIME Min.	Travel Distance	Velocity	
33.33	10	0.3	
Exp.Time Hrs.			
0.56			

#### Film DENSITY vs. VELOCITY

NEW Velocity In/Min	Film DENSITY Wanted	First Film DENSITY	Old Velocity In./Min.
0.50	2	1	1

**Volume of a Sphere**

Volume	Sphere Diameter
0.0655	0.5

**Area of a Circle**

Area (Sq. Inches)	Circle Diameter (Inches)
0.0123	0.125


TO FIND VALUES IN LEFT COLUMN, TYPE VALUES  
IN THE BOXES ON THE RIGHT.

by Derrill Rikard

### ULTRASONIC CALCULATIONS

#### SNELLS LAW

Angle i (in Degrees)	Angle r (in Degrees)	Velocity 1	Velocity 2
29.671	90	1.49	3.01
Angle r (in Degrees)	Angle i (in Degrees)	Velocity 2	Velocity 1
88.482	15.23	5.67	1.49
Velocity 1 Longitudinal	Angle i (in Degrees)	Velocity 2	Angle r (in Degrees)
1499.643	20.7	3250	50
Velocity 2 Shear	Angle i (in Degrees)	Velocity 1	Angle r (in Degrees)
3250.774	20.7	1500	50



#### Acoustic Impedance

Impedance-Z	Mat. Density g/cm 3	UT velocity
46800.000	7.8	6000

#### Amplitude / Decibels

Decibels	Amplitude 1	Amplitude 2
-6.021	20	40
Ratio A1/A2	Decibels	
17.783	25	

#### Wavelength

Wavelength	Velocity	Frequency
0.333	11	33

#### LENGTH of NEAR ZONE

Near Zone	Crystal Diameter	Wavelength
0.047	0.25	0.333

#### BEAM DIVERGENCE

Degrees 1 / 2 Angle	Wavelength	Crystal Diameter	
1.679	1.2	25	
Degrees 1 / 2 Angle	Long.Velocity in MATL	Frequency	Crystal Diameter
#DIV/0!			

#### REFLECTED ENERGY



Reflected Energy	Impedence 1 (Z-1)	Impedence 2 (Z-2)
0.233	2.3	6.6

### Angle Beam Formulae

LEG Length      THICKNESS of MATL.      Transducer Angle in Degrees  
1.414      1      45

V-PATH      THICKNESS of MATL.      Transducer Angle in Degrees  
2.828      1      45


SKIP Distance      THICKNESS of MATL.      Transducer Angle in Degrees  
2.000      1      45



### DEFECT LOCATION in 1st LEG


SURFACE DISTANCE      Soundpath Distance      Transducer Angle in Degrees  
1.414      2      45

DEPTH (1st LEG)      Soundpath Distance      Transducer Angle in Degrees  
1.061      1.5      45



### DEFECT LOCATION in 2nd LEG

DEPTH (2nd LEG)      THICKNESS of MATL.      Soundpath Distance      Transducer Angle in Degrees  
0.586      1      2      45



### FIRST CRITICAL ANGLE

1st Crit. Angle Degrees      Long. Vel. MAT.2      Long. Veloc. MAT.1  
28.850      5.72      2.76

### SECOND CRITICAL ANGLE

2nd Crit. Angle Degrees      Long. Veloc. MAT.1      Shear Veloc. MAT.2  
66.051      2.76      3.02